

COMBIVIS Studio HMI 4.0



Lesson 9 Visual Basic Scripts





You will learn in this lesson...



Goal:

- Create a:
 - Visual Basic Script





VB – scripts



- The language of the script based on "Visual basic for Application"
- Because of the limited debugopportunities the programm should be small and clear
- A script <u>can</u> be repeated frequently (e.g. for special mathematic operations). Use the "DoEvents" For those loops to avoid freezing of the project



Function GetPlainText ru00(value As Integer) As String

```
Select Case value
Case 0
    GetPlainText ru00
                         = "no operation"
    GetPlainText_ru00
                         = "ERROR overpotential"
    GetPlainText ru00
                         = "ERROR underpotential"
Case 3
    GetPlainText ru00
                         = "ERROR phase failure"
Case
    GetPlainText ru00
                         = "ERROR overcurrent"
    GetPlainText ru00
                         = "ERROR overheat internal"
```






VB – scripts



 Scripts can be activated via buttons or events

 A script can be activated once, after the start of the project







VB – scripts





Also scripts can be embedded in objects:

- Select an object
- open "script explorer"

Choose an event

 Open the VK library by clicking on "search"









Practice



1. Create a script in the button-object "Light On" ("Screen1") which indicates the status "Light turned ON" if it's turned on and "Light turned OFF" if it's turned of via a message box.

Note: The command for a message box is: "MsgBox Message (, Type) (,Title)"

Message : Type String

Type (Optional) (see Help)

Title (Optional) (see Help)

2. Create a script ("StartScript") which sets the value of "Counter" to 99 and the language to "English" at every start of the project.

Note: The methode of setting the language can be found on "CommandLanguageCmdTarget".







COMBIVIS Studio HMI 4.0



✓ Lesson 9



